



METER
ENVIRONMENT

TEROS 21 FIRMWARE UPDATER VERSION 4.06

NOTE: Please check with [METER Support](#) before updating sensor firmware. Sensor firmware updates are not typically necessary and should only be carried out if needed.

[Install TEROS 21 updater \(version 4.06\)](#)

To increase TEROS 21 dry end accuracy and reduce temperature sensitivity in the plant available range, the ceramic formula and sensor calibration have been improved, limiting the dry end measurement to -2000 kPa. Because of this change, older sensors (Serial T12-00009999 and lower) cannot be updated to Firmware Version 4.06.

If you need to update a TEROS 21 with firmware T21-00009999 and lower, please use firmware updater version 3.89.

[Install TEROS 21 updater \(version 3.89\)](#)